










# knitking

*magazine*



jan/feb '72



1. Treble Transfer Tools for rapid transfer of stitches and for Cable Stitch. \$1.50 pair plus 25¢ shipping.

2. 33 Needle Multi-Transfer Tool. For decreasing in the middle of a row. \$3.25 plus 25¢ shipping.

3. KNITKING Weaving Accessory (for AM 3 machine). Weaves an additional thread into your knitting and produces patterns with a woven appearance. \$6.95 plus 30¢ shipping.

4. Converta Tape. For simple and speedy charting of custom knits. \$6.95 plus 30¢ shipping.

**accessories**

5. Reversing Bar. For easy hem turning or reversing of knitting. \$17.95 plus \$1.50 shipping.

6. Adjustable Needle Selector. For setting unevenly spaced pattern stitches. \$3.50 plus 25¢ shipping.

7. KNITKING Pattern Stitch Cards (for AM 3 machine only). 48 Pattern Cards with 96 beautiful patterns in color and black and white. Simple row by row instructions. \$9.50 plus 95¢ shipping.

8. Yarn Winder and Skein Holder. Heavy cast frame and nylon gears. \$15.95 plus \$1.00 shipping. Without Skein Holder \$12.95 plus \$1.00 shipping.

California residents add 5% Sales Tax

**KNITKING • 1128 Crenshaw Blvd., Los Angeles, California 90019**

# knitking magazine

INDEX	PAGE NO.
DK 7965 Woman's 3-piece Suite . . . . .	14
DP 8066 Woman's Pullover . . . . .	16
DK 8059 Woman's Jacket and Hot Pants . . . . .	16
DK 8060 Woman's Pullover and Leotites . . . . .	18
DP 8000 Woman's Pullover . . . . .	19
DK 7995 Woman's 2-piece Suit . . . . .	20
DK 8004 Woman's Dress . . . . .	22
MK 5329 Girl's Dress . . . . .	22
MK 5330 Girl's Tunic Dress and Slacks . . . . .	24
HP 3656 Man's Pullover . . . . .	25
HP 3654 Man's Slacks and Pullover . . . . .	26
MK 5300 Girl's Coat, Hat, Mittens and Scarf . . . . .	27
KK 5306 Boy's Jacket and Hat . . . . .	28
KK 5299 Child's Slacks and Pullover . . . . .	29
KG 1934 Long Scarf . . . . .	30
KG 1935 Long Scarf . . . . .	30
KG 1937 Woman's Hat . . . . .	30
KG 1936 Woman's Shoulder Bag . . . . .	31
KG 1938 Baby Car Bed Cover, Kiddie Car Coat, Booties . . . . .	31



**FRONT PIECE**

**DK 8065**

Whether your mood is sportive or elegant, you'll revel in our newest selection of KNITKING knits to start the year 1972 off with a bang...!! So treat yourself to the sumptuous 3-part Cover

Model Suit DK 8065. It includes a Blazer, Skirt and Tank Top. All in Sizes 10, 12 and 14. See page

**BACK COVER DK 8059 and DK 8060**

Like Robin Hood, you can go your 'Merry Way' in a brand new sports outfit. Knit the Jacket and Hot Pants in Stockinette Stitch with Bands and Collar on Pullover, the Leotites in Ribbing. All in Sizes 8, 10 and 12. DK 8059: Jacket and Hot Pants. See page 16. . DK 8060: Pullover and Leotites. See page 18.

Publisher: KNITKING CORPORATION, 1128 Crenshaw Blvd., Los Angeles, Calif. 90019. Telephone: WEbster 8-2079. Published bi-monthly. Subscriptions: USA - \$6.00 annually, single copies \$1.50; Canada - \$7.00; other parts of the world - \$10.00. The entire contents of KNITKING MAGAZINE are copyright and must not be reproduced in any shape or form without the express permission, in writing of the publisher. COPYRIGHT © by KNITKING CORPORATION 1971.

Printed by George Rice & Sons, Los Angeles, California



KNITKING  
1128 Crenshaw Blvd.  
Los Angeles, Calif. 90019

## ORDER IT NOW!

Every reader of KNITKING MAGAZINE needs the new big beautiful KNITKING YARN CATALOGUE with 329 actual yarn samples . . . the finest from around the world in an unbelievable range of colors.

I enclose one dollar . . .  
Please RUSH my beautiful new  
KNITKING YARN CATALOGUE to me at:

Name \_\_\_\_\_

Address \_\_\_\_\_


City \_\_\_\_\_

State \_\_\_\_\_

Zip \_\_\_\_\_



## BOOKS by KNITKING



### NEW VOLUME AVAILABLE NOW

A complete seventh volume of KNITKING MAGAZINES with a flexible, transparent plastic cover and specially bound so that it will stay open at any page, is available at the special price of \$6.95 (plus 95 cents mailing costs).

If purchased separately the magazines would cost a total of \$9.00.

The volume contains over 120 fully illustrated complete stylish patterns for all members of the family together with many valuable, practical knitting hints.

There is a very limited number of these volumes available and it will undoubtedly become a collectors item.

If you already have the entire set it will almost certainly be well thumbed and marked. Why not purchase a perfect mint condition volume for your bookshelf and ready reference at any time.

Place your order today and avoid disappointment. Send it to KNITKING MAGAZINE, 1128 Crenshaw Boulevard, Los Angeles, California 90019.

#### PRACTICAL KNITTING HINTS

We call this book the TEXT BOOK for machine knitters because it answers the many questions that occur in machine knitting, from preparing to knit, taking measurements, shaping, making buttonholes, special effects, bindings, bands and edges, etc., through finishing and blocking. It sells for **\$2.95**

40 cents mailing  
Calif. residents add 5% Sales Tax

I enclose \$7.90

Please RUSH my bound Seventh Volume of KNITKING MAGAZINE to me at:

Name \_\_\_\_\_

Address \_\_\_\_\_

City \_\_\_\_\_ State \_\_\_\_\_ Zip \_\_\_\_\_

# knitking *magazine*

As we enter the New Year, we wish our Readers happiness and success in their endeavors . . . Our resolution is to continue to improve KNITKING MAGAZINE and our services to Customers . . . Our hope is that 1972 will see peace throughout the world.

Readers will note some modifications in the printed instructions in this issue . . . At the beginning of every Pattern, we tell you the amount of Yarn you need, what tensions to knit at and the Stitch and Row Gauge needed for each individual size . . . The separation of each size makes it easier for you to select and order the materials for the size garment you wish to knit . . . We urge you to use beautiful KNITKING YARNS and insure the quality of garment that you and KNITKING Patterns deserve.

Among our plans for the future is the inclusion of some Color Illustrations inside the Magazine, but we can only do this when our subscriber list reaches a certain target number . . . Color printing is terribly expensive and as KNITKING MAGAZINE still operates at a loss, we cannot at this time, afford the additional cost . . . But our subscriber list grows steadily and as soon as it is financially possible, you will have Color Pictures.

If you are a subscriber who shares your magazine with other knitting machine owners, you can help us reach our target by encouraging your friends to place their own subscriptions . . . We receive many subscriptions from new readers as a result of referrals by old readers . . . so . . . if you know any knitting machine owners that do not subscribe, show them a copy of our beautiful KNITKING MAGAZINE and encourage them to join the family.

We are featuring several of the popular 'Skinny Rib' Sweaters for Men, Women and Children in the forthcoming March-April issue. The front Cover garment will be a stylish and slimming two color Twin-Set designed with the larger Women in mind . . . The back Cover features another two-piece Set, this time it is a Pullover and a long Vest; both are knitted in three colors . . . We also have some good looking Dresses, Pants outfits, some clothes for the youngsters and a selection of Gift items . . . Watch for it . . . it will be a good issue.



LETTER  
from the  
PUBLISHER





**DP 8066**

Layer on layer . . . Wear a classic Stockinette Stitch Pullover under the Tank Top (which is part of the Cover Suit DK 8065) for that layered look. K1, P1 Ribbing is used for the bands and Collar. Sizes 10, 12, 14. All knitted with KNITKING Subita Crepe 2 x 4.

See page 16\*



**DP 8000**

It's a beautiful long Pullover that is slightly fitted at the waistline. An Eyelet and Cable Design is on the front and back sections, with Yoke and Sleeves in Stockinette Stitch. The Neckband and long Cuff on the Sleeves are a 1 x 1 Rib. In Sizes 10, 14 and 16.


See page 19



**DK 7995**

You'll certainly want to knit this bright and figure flattering Popcorn Suit. The Pattern Stitch is easy and very attractive. Be sure to read our Practical Knitting Hints on page 32 of this issue. In sizes 10, 14 and 18. See page 20





**DK 8004**

En route to anywhere . . . ! A long romantic Dress makes you a vision of loveliness. The Bodice and lower section of puffed Sleeves are in Purl 3, Knit 1 Ribbing. Tie a brilliant sash at waistline. Sizes 6, 10 and 12; all knitted with beautiful cable twisted KNIT-KING Subita Crepe 2 x 3. See page 22




**MK 5329**

Your teen age Girl will flip over a dress designed to flatter the young figure. It's knitted in Stockinette Stitch with a Norwegian Design trim and a flirty Ruffle around the lower edge. Size 7/8 and 11/12 are knitted with KNITKING Subita Crepe 2 x 3; Size 13/14 with Crocus Crepe. See page 22




**MK 5330**

All perfect . . . !! As a Dress, or as a Tunic to be worn over the Slacks. She'll love the feminine Embroidery trim of knitted Flowers and Crochet Edgings . . . Both Tunic Dress and Slacks are knitted in Stockinette Stitch. Size 5/6, use KNITKING Subita Crepe 2 x 3; Size 7/8 and 9/10, Subita Dralon 3-ply. See page 24



**HP 3656**

Every Man's choice for a 'V' necked Pullover. Knit it in Stockinette Stitch with a Design down the front section. Rib all Bands. Sizes 36, 38 and 42. Knitted with KNITKING Sonika Dralon and Double Knitting. See page 25



**HP 3654**

Introduce him to the very latest in Slack Suits for Men . . . Stockinette Stitch and a Cable Design on the Pullover with Ribbing for Collar and Bands. Sizes 36, 38 and 40. Knitted with KNITKING Subita Crepe 2 x 4 and Sonika Dralon. See page 26

**KK 5306**

Brighten your Boys life and keep him warm as well, with a handsome zippered Jacket and Hat to match. Three colors are used for the Pattern Stitch that follows a Chart. Size 4, 6, 8. Knit each size with machine washable KNITKING Sonika Dralon.


See page 28



**MK 5300**

Sister is delighted with her cozy 4-piece ensemble of Coat, Hat, Scarf and Mittens. A beautiful warm outfit for that special little Girl. Sizes 3 to 4; 5 to 6 and 7 to 9. All sizes are knitted with KNITKING Sonika Dralon and can be thrown in your washer and dryer.

See page 27



KK 5299

Made for action . . . Boy or Girl can wear the nicely fitted Pants and warm Pullover. Knit the Pants in Stockinette Stitch. The Pullover has a small Cable down the front section. Rib all bands. Sizes 2, 3 and 4. All are knitted with hard wearing, easy care KNIT-KING Fortissima. See page 29

**KG 1936**

It looks like crochet . . . but it's KNITKING knitted and everyone seems to want one. You can knit this Shoulder Bag in less than a wink . . . ready to put together and line. The Pattern is made over every 3rd needle. Easy-care KNITKING Leacril is the yarn.

See page 31.




**KG 1934 and KG 1935**

Take your pick . . . or knit them both. Fling a long feather light scarf around your throat. One is knitted in a 1 x 1 Rib and striped in two colors . . . the other is knitted in Fisherman's Rib. Both are made with soft and warm KNITKING Subita Dralon 2-ply.

See page 30





**KG 1938**

Baby Time . . . !! We present our very favorite Gift for a brand new Baby. It includes a Coat with attached Hood, Car Bed Cover and Booties. Knit them in an easy Pattern Stitch with downy soft KNITKING Subita Dralon 2-ply. Machine wash and dry.

See page 31

**KG 1937**

Pull a warm Hat over your ears to keep out the wind and cold. It is deep enough to tuck long hair under and it stretches to fit everyone. Knit it with KNITKING Frigate or Leacril. See page 30





Move the Cam Box to the left side, put all the needles into working position, turn the Row Counter back to 200 and complete the left half. Follow the instructions from \*.

\*ON CAM BOX SIDE, bind off 3 sts. after Rows 201, 203; 2 sts. after Rows 205, 207; 1 st. after Rows 209, 211, 213, 215, then knit to Row 220 and bind off the remaining 11 sts.



ROWS 164 to 200: Knit even, then bind off the center 28 sts. and put the needles on the left side into holding position and complete the right half first.

ON CAM BOX SIDE, bind off 4 sts. after Rows 136, 137, 138, 139; 3 sts. after Rows 140, 141, 142, 143; 2 sts. after Rows 144, 145, 146, 147, 148, 149; 1 st. after Rows 150, 151, 152, 153, 154, 155, 156, 157, 158, 159, 160, 161, 162, 163.


ON EACH SIDE, decrease 1 st. after Rows 44, 68, 92, 116, then knit to Row 136.

ROWS 0 to 44. Knit even, then change to stockinette stitch.



Cast on 124 sts. and work K1, P1 Ribbing.



Cast on 72 sts. and work 18 rows K1, P1 Ribbing, then bind off all sts.



Cast on 150 sts. and work 18 rows K1, P1 Ribbing, then bind off all sts.




ON CAM BOX SIDE, bind off 4 sts. after Rows 170, 171, 172, 173; 3 sts. after Rows 174, 175, 176, 177; 2 sts. after Rows 178, 179, 180, 181, 182, 183, 184, 185; 1 st. after Rows 186, 187, 188, 189, 190, 191, 192, 193, 194, 195, 196, 197, 198, 199, 200, 201, 202, 203, 204, 205, 206, 207, 208, 209; 2 sts. after Rows 210, 211, 212, 213, 214, 215; 3 sts. after Rows 216, 217, 218, 219; 12 sts. after Row 220.

ON EACH SIDE, increase 1 st. after Rows 30, 38, 46, 54, 62, 70, 78, 86, 92, 98, 104, 110, 116, 122, 128, 134, 140, 146, 152, 158, 164, then knit to Row 170.

ROWS 0 to 30: Knit even, then begin the color stripes.

Cast on 62 sts. with color 1.




Decrease 2 sts. for each Dart after Row 204, then again after Rows in (. Continue to decrease 1 st. on each side after Rows 210, 212, 220, 220, 228, 228, 236, 236, 244, 244, 252, 252, 252, then knit to Row 282 and bind off the remaining 95 sts.

ON EACH SIDE, decrease 1 st. after Rows 54, 66, 78, 90, 102, 114, 126, 138, 150, 160, 170, 180, 190, 200, then knit to Row 204.

ROWS 0 to 54, Knit even.

Cast on 163 sts. and work stockinette stitch.



Decrease 2 sts. for each Dart after Rows (. ON EACH SIDE, decrease 1 st. after Rows 210, 216, 220, 228, 228, 236, 240, 244, 252, 252, then knit to Row 282 and bind off the remaining 107 sts.

Work the Front the same as the Back to Row 202.

# DP 8066

**SIZE:** 10 (Bust 32½"-33") 12 (Bust 34"-35") 14 (Bust 36"-37")  
**YARN:** Subita Crepe 2 x 4 8  
**TENSION:** 4 to 6 5 to 7 6 to 8  
**GAUGE:** 2" 17 sts, 24 rows 16 sts, 23 rows 15 sts, 22 rows

The instructions are the same for all sizes. **PATTERN:** Stockinette stitch with K1, P1 Ribbing for Neckband and edges, **INCREASES** and **DECREASES:** Full fashion (see **KNITTING** Practical Knitting Hints book, pages 14 to 17).






**FINISHING:** Block all sections. Join front and back sections at sides and shoulders. Sew sleeves together and set in. Sew one edge of Collar to inside and one edge to outside of neckline. Work 1 row of single crochet around edges of opening. Make 3 loops and sew on buttons.

# DK 8059

**SIZE:** 8 (Bust 31½"-32½") 10 (Bust 32½"-33") 12 (Bust 34"-35")  
**YARN:** Subita Dralon 3-ply 10  
**50gr. balls** 8 C-1 for Jacket 12 C-1 for Jacket Double Knitting  
**TENSION:** 4 to 6 5 to 7 6 to 8  
**GAUGE:** 2" 16 sts, 22 rows 15 sts, 20 rows 14 sts, 19 rows

The instructions are the same for all sizes. **PATTERN:** Stockinette stitch. **INCREASES** and **DECREASES:** Full Fashion (see **KNITTING** Practical Knitting Hints book, pages 14 to 17).

**FINISHING:** Block all sections. **JACKET:** Join side seams and shoulder. Sew sleeves together and set in. Turn under 2" at front edges for facing. Turn 2" at top of pocket to inside, then sew hem and side of hem. Sew pockets to Jacket (see picture). Fold 1½" at top of pocket to outside and sew on buttons. Fold collar in half lengthwise and weave the short edges together. Sew collar to Jacket with one edge on the inside and one on the outside of neckline, leaving 1" free on each edge. Hem lower edge of Jacket, finish buttonholes and sew on buttons. **HOTPANTS:** Join pants at center front and back. Sew leg seams and make 1½" hem on leg edges. Fold upper edge (waistline) to wrong side and make a hem, then insert elastic.



Move the Cam Box to the left side, put Row Counter back to 238 and complete the left side. Follow the instructions from \*.

\*ON CAM BOX SIDE, bind off 3 sts, after Rows 239 (ODD ROWS = NECK SHAPING), 241, 243; 2 sts, after Rows 245, 247; 1 st, after Rows 249, 251, 253, 255, 257; 4 sts, after Rows 258 (EVEN ROWS = SHOULDER SHAPING), 260, 262; 5 sts, after Rows 264, 266, 268, 270, 272.

ON CAM BOX SIDE, bind off 4 sts, after Rows 172, 173; 3 sts, after Rows 174, 175, 176, 177; 2 sts, after Rows 178, 179, 180, 181; 1 st, after Rows 182, 183, 184, 185, 186, 187, then knit to Row 238, bind off the center 12 sts, put all the needles on the left side into holding position and complete the right side first.

ON OPPOSITE SIDE OF CAM BOX, put 7 needles into holding position after Rows 142, 143, 144, 145, 146, 147, 148, 149, 150, 151. ON OPPOSITE SIDE OF CAM BOX, bring all the needles back into working position after Rows 152, 153, then knit to Row 172.

Work the front section the same as the back to Row 142, then work Short Rows.

Move the Cam Box to the left side, put Row Counter back to 220 and complete the left side. Follow the instructions from\*.

ON CAM BOX SIDE, bind off 4 sts, after Row 248 (EVEN ROWS = SHOULDER SHAPING); 9 sts, after Row 249 (ODD ROWS = NECK SHAPING); 4 sts, after Row 250; 3 sts, after Row 251; 4 sts, after Row 252; 3 sts, after Row 253; 5 sts, after Row 254; 3 sts, after Row 255; 5 sts, after Row 256; 2 sts, after Row 257; 5 sts, after Row 258; 2 sts, after Row 259; 5 sts, after Row 260; 2 sts, after Row 261; 5 sts, after Row 262.

ON CAM BOX SIDE, bind off 4 sts, after Rows 162, 163; 3 sts, after Rows 164, 165, 166, 167; 2 sts, after Rows 168, 169, 170, 171; 1 st, after Rows 172, 173, 174, 175, 176, 177. Knit to Row 220. Put 61 needles on the left side into holding position and complete the right side first. \*Knit to Row 248.

ON EACH SIDE, decrease 1 st, after Rows 70, 88, 106, 124, 142, then knit to Row 162.

ROWS 23 to 70: Knit even.  
 ROWS 0 to 22: Knit even, then change to stockinette stitch.

Cast on 146 sts, and work K1, P1 Ribbing, then bind off all sts.

Cast on 137 sts. Work 28 rows K1, P1 Ribbing, then bind off all sts.





# DK 8060

**SIZE:** 8 (Bust 31 1/2"-32 1/2") 10 (Bust 32 1/2"-33") 12 (Bust 34"-35")  
**YARN:** Subita 2 x 3 Crocus Crepe Subita 2 x 4  
 50gr. balls 10 for Pullover 10 for Leotites  
**TENSION:** Stock. 4 to 5 6 to 8  
 Rib. 5 to 7 6 to 8  
**GAUGE:** 17 sts, 25 rows 16 sts, 23 rows 15 sts, 22 rows

The instructions are the same for all sizes. **PATTERN:** Pullover, stockinette stitch with bands and collar, K1, P1 Ribbing. Leotites, K1, P1 Ribbing with foot sections and hem at waistline stockinette stitch. **INCREASES and DECREASES:** Full Fashion on stockinette sections, edge increases and decreases on ribbed sections. (see **KNITTING Practical Knitting Hints book**).

**FINISHING:** Block all sections. **PULLOVER:** Join front and back sections at sides and shoulders. Sew sleeves together and set in. Sew short sides of Collar to form circle, fold in half lengthwise and sew one edge to inside and one to outside of neckline. **LEOTITES:** Join sections at center back and center front. Sew leg seams together. Weave the sts. held on stitch holders for heel, then sew instep to sole at sides. Make hem at waistline and insert elastic.



Cast on 151 sts. and work 46 rows K1, P1 Ribbing, then bind off all sts.

\*ON CAM BOX SIDE, bind off 4 sts. after Row 223 (ODD ROWS = NECK SHAPING); 3 sts. after Rows 225, 227; 2 sts. after Rows 229, 231; 1 st. after Rows 233, 235, 237, 239, 241; 3 sts. after Rows 244 (EVEN ROWS = SHOULDER SHAPING), 246, 248; 4 sts. after Rows 250, 252, 254, 256, 258. Bring the Cam Box to the left side, turn the Row Counter back to 222 and complete the left half. Follow the instructions from\*.

Work the front the same as the back to Row 222, bind off the center 13 sts, put all the needles on the left side into holding position and complete the right half first.




Move the Cam Box to the left side, turn the Row Counter back to 244 and complete the left side. Follow instructions from\*.

\*ON CAM BOX SIDE, bind off 3 sts. after Rows 244 (EVEN ROWS = SHOULDER SHAPING) 4 sts. after Row 245 (ODD ROWS = NECK SHAPING); 3 sts. after Row 246; 4 sts. after Row 247; 3 sts. after Rows 248, 249; 4 sts. after Row 250; 3 sts. after Row 251; 4 sts. after Rows 252; 3 sts. after Row 253; 4 sts. after Rows 254, 256, 258.

ON CAM BOX SIDE, bind off 4 sts. after Rows 166, 167; 3 sts. after Rows 168, 169, 170, 171; 2 sts. after Rows 172, 173, 174, 175; 1 st. after Rows 176, 177, 178, 179, then knit to Row 244, bind off the center 17 sts, put all the needles on the left side into holding position, and complete the right half first.

ROWS 25 to 166: Knit even.  
 ROWS 0 to 24: Knit even, then change to stockinette stitch.

Cast on 141 sts. and work K1, P1 Ribbing.



Make the second section with reverse shaping, casting on from right to left. Cam Box will be on the left side at Row 0.

Work short rows for the heel. ON OPPOSITE SIDE of Cam Box, put into holding position, 1 needle after Rows 622, 623, 624, 625, 626, 627, 628, 629, 630, 631; 2, needles after Rows 632, 633, 634, 635. ON OPPOSITE SIDE of Cam Box, bring back into working position 2 needles after Rows 636, 637, 638, 639; 1 needle after Rows 640, 641, 642, 643, 644, 645, 646, 647, 648, 649, then knit to Row 656 and put the remaining 31 sts. onto a stitch holder.

ON EACH SIDE, increase 1 st. after Rows 602, 606, 610, 614, 618, then knit to Row 622 and bind off 5 sts. on each side (use a separate strand of yarn for opposite side).

Work short Rows for the Toe. ON OPPOSITE SIDE of Cam Box, put into holding position, 1 needle after Rows 516, 517, 518, 519, 520, 521, 522, 523, 524, 525, 526, 527, 528, 529; 2 needles after Rows 530, 531, 532, 533. ON OPPOSITE SIDE of Cam Box, bring back into working position, 2 needles after Rows 534, 535, 536, 537; 1 needle after Rows 538, 539, 540, 541, 542, 543, 544, 545, 546, 547, 548, 549, 550, 551, then knit even to Row 602.

ROWS 447 to 516: Knit even, then transfer the ribber sts. to the main machine and work stockinette stitch.

ON EACH SIDE, decrease 1 st. after Rows 312, 318, 324, 330, 336, 342, 348, 354, 360, 366, 372, 378, 384, 390, 396, 402, 406, 410, then knit to Row 446 and put 32 sts. on Cam Box side onto a stitch holder.

ON EACH SIDE, decrease 1 st. after Rows 160, 164, 168, 172, 176, 180, 184, 188, 192, 196, 200, 204, 208, 212, 216, 220, 224, 228, 232, 236, 240, 246, 252, 258, 264, 270, 276, then knit to Row 312.

ON EACH SIDE, increase 1 st. after Rows 96, 102, 108, 114, 120, 124, 128, 132, 136, 140, 144, 148, 152, 156, then knit to Row 160.

ROWS 33 to 96: Knit even.

Knit 2 rows. ON OPPOSITE SIDE of Cam Box, bring back into working position 12 needles after Rows 20, 22, 24, 26, 28; 50 needles after Row 30. After Row 32, all the needles are in working position and continue K1 P1 Ribbing.

ROWS 0 to 18: Knit even, then put 110 sts. on opposite side of Cam Box into holding position for working short rows. Of the remaining 15 sts., transfer every other st. to the Ribber. As you bring the needles back into working position, you must transfer the appropriate sts. to the Ribber.


Cast on 125 sts. and work stockinette stitch for the band.








Work the second front section with reverse shapings, casting on from right to left. (Cam Box will be on the LEFT side at Row 0). Omit the buttonholes.



Cast on 126 sts, with color 1, work stockinette st. and Short Rows. ON OPPOSITE SIDE of CAM BOX put into holding position 42 needles after Rows 0, 1. ON OPPOSITE SIDE of CAM BOX bring back into working position 7 needles after Rows 2, 3, 4, 5, 6, 7, 4 needles after Rows 8, 9, 10, 11, 12, 13; 3 needles after Rows 14, 15, 16, 17, 18, 19, then knit over all 126 sts. to Row 64. ON OPPOSITE SIDE of CAM BOX put into holding position 2 needles after Rows 64, 65, 66, 67, 68, 69; 3 needles after Rows 70, 71, 72, 73; 10 needles after Rows 74, 75, 76, 77, 78, 79. After Row 80 bring all needles back into working position, then bind off all sts.



ON CAM BOX SIDE, bind off 4 sts. after Row 232; 3 sts. after Rows 236, 240; 2 sts. after Rows 244, 248; 1 st. after Rows 252, 256, then knit to Row 345.

ON OPPOSITE SIDE of CAM BOX (DART SIDE) decrease 1 st. after Rows in ( ). ON CAM BOX SIDE (SIDE SEAM) decrease 1 st. after Rows 10, 26, (32), 42, (54), 58, 74, (76), then knit to Row 96. ON DART SIDE increase 1 st. after Rows in ( ). ON SIDE SEAM SIDE, increase 1 st. after Rows 96, (96), (120), 126, (144), 156, (168), but do not knit after last increase. Put the 33 needles into holding position and bring the 47 needles on the left side (right side for second section) into working position. ON CAM BOX SIDE, decrease 1 st. after Rows 10, 32, 54, 76. Make a buttonhole after Row 84 over the 7th-11th sts. counting from the left side, then knit to Row 96. ON CAM BOX SIDE, increase 1 st. after Rows 96, 120, 144. (Make a buttonhole after Row 154), 168, but do not knit after last increase. Move the Cam Box to the right side, bring all needles into working position and with Row Counter at 168 continue to work over all 80 needles. ON CAM BOX SIDE, increase 1 st. after Row 186, make a buttonhole after Row 224, then knit to Row 232.

ROWS 0 to 10: Knit even, then put 47 needles on the left side (right side for second section) into holding position and work the DART.

Cast on 82 sts, with color 1 and work the Pop-Corn Pattern.

Work the left side facing with reverse shapings, casting on from right to left. (Cam Box will be on the LEFT side at Row 0). Omit the buttonholes.

ON CAM BOX SIDE, increase 1 st. after Rows 145, 153, 161, 169, 177, 185, 193, 201, 209, 215, then again after Rows in ( ). Knit to Row 216. ON CAM BOX SIDE (NECK SIDE) bind off 18 sts. after Row 216; 6 sts. after Row 218; 4 sts. after Row 220; (221), 3 sts. after Row 222; 2 sts. after Rows 224, 226, (227), 228; 1 st. after Rows 230, 232. For SHOULDER bind off 3 sts. after Rows 233, 235, 237.

ROWS 0 to 145: Knit even and make buttonholes after Rows 52, 96, and 140 over the 7th-11th sts. counting from the right side.

Cast on 36 sts, with color 1 and work stockinette st.

Work the left side facing with reverse shapings, casting on from right to left. (Cam Box will be on the LEFT side at Row 0). Omit the buttonholes.

ON CAM BOX SIDE, increase 1 st. after Rows 145, 153, 161, 169, 177, 185, 193, 201, 209, 215, then again after Rows in ( ). Knit to Row 216. ON CAM BOX SIDE (NECK SIDE) bind off 18 sts. after Row 216; 6 sts. after Row 218; 4 sts. after Row 220; (221), 3 sts. after Row 222; 2 sts. after Rows 224, 226, (227), 228; 1 st. after Rows 230, 232. For SHOULDER bind off 3 sts. after Rows 233, 235, 237.

ROWS 0 to 145: Knit even and make buttonholes after Rows 52, 96, and 140 over the 7th-11th sts. counting from the right side.

Cast on 36 sts, with color 1 and work stockinette st.

Bring the needles on the left side into working position, knit 1 row in pattern to the left side, turn the Row Counter back to 346 and complete the left half. Follow the instructions from\*.

\*ON CAM BOX SIDE, bind off 2 sts. after Row 346 (EVEN ROWS = SHOULDER SHAPING); 3 sts. after Row 347 (ODD ROWS = NECK SHAPING); 2 sts. after Row 348; 3 sts. after Rows 349, 350; 2 sts. after Row 351; 3 sts. after Row 352; 2 sts. after Row 353; 3 sts. after Row 354; 2 sts. after Row 355; 3 sts. after Rows 356, 358.

ON CAM BOX SIDE, bind off 2 sts. after Rows 334, 335, 336, 337, 338, 339, 340, 341, 342, 343, 344, 345, then knit to Row 346, bind off the center 12 sts., put the needles on the left side into holding position and complete the right half first.

ON CAM BOX SIDE, bind off 4 sts. after Rows 212, 213; 3 sts. after Rows 216, 217, 220, 221; 2 sts. after Rows 224, 225, 228, 229; 1 st. after Rows 232, 233, 236, 237, then knit to Row 334.

ON OPPOSITE SIDE of CAM BOX (DART SIDE) decrease 1 st. after Rows in ( ). ON CAM BOX SIDE (SIDE SEAM) decrease 1 st. after Rows 10, (10), 26, (32), 42, (54), 58, 74, (76), then knit to Row 96. ON DART SIDE increase 1 st. after Rows in ( ). ON SIDE SEAM increase 1 st. after Rows 96, (96), (120), 126, (144), 156, (168) but do not knit after last increase. Put the 39 needles into holding position, bring the center 50 sts. into working position and turn the Row Counter back to 10. ON EACH SIDE, decrease 1 st. after Rows 10, 32, 54, 76, then knit to Row 96. ON EACH SIDE, increase 1 st. after Rows 96, 120, 144, 168, but do not knit after last increase. Put the 50 needles into holding position, bring the 41 needles on the left side into working position and turn the Row Counter back to 10. ON OPPOSITE SIDE of CAM BOX (SIDE SEAM) decrease 1 st. after Rows in ( ). ON CAM BOX SIDE (DART SIDE) decrease 1 st. after Rows 10, (10), (26), 32, (42), 54, (58), (74), 76, then knit to Row 96. ON SIDE SEAM increase 1 st. after Rows in ( ). ON DART SIDE, increase 1 st. after Rows 96, (96), 120, (126), 144, (156), 168, but do not knit after last increase. Move the Cam Box to the right side, bring all needles back into working position and with Row Counter at 168 continue to knit over all 128 needles. ON EACH SIDE, increase 1 st. after Row 186, then knit to Row 212.

ROWS 0 to 10: Knit even, then put 91 needles on the left side into holding position and work the DARTS.


Cast on 132 sts, with color 1 and work the Pop-Corn Pattern.

Work the left side facing with reverse shapings, casting on from right to left. (Cam Box will be on the LEFT side at Row 0). Omit the buttonholes.

ON CAM BOX SIDE, increase 1 st. after Rows 145, 153, 161, 169, 177, 185, 193, 201, 209, 215, then again after Rows in ( ). Knit to Row 216. ON CAM BOX SIDE (NECK SIDE) bind off 18 sts. after Row 216; 6 sts. after Row 218; 4 sts. after Row 220; (221), 3 sts. after Row 222; 2 sts. after Rows 224, 226, (227), 228; 1 st. after Rows 230, 232. For SHOULDER bind off 3 sts. after Rows 233, 235, 237.

ROWS 0 to 145: Knit even and make buttonholes after Rows 52, 96, and 140 over the 7th-11th sts. counting from the right side.

Cast on 36 sts, with color 1 and work stockinette st.



Work the left side facing with reverse shapings, casting on from right to left. (Cam Box will be on the LEFT side at Row 0). Omit the buttonholes.

ON CAM BOX SIDE, increase 1 st. after Rows 145, 153, 161, 169, 177, 185, 193, 201, 209, 215, then again after Rows in ( ). Knit to Row 216. ON CAM BOX SIDE (NECK SIDE) bind off 18 sts. after Row 216; 6 sts. after Row 218; 4 sts. after Row 220; (221), 3 sts. after Row 222; 2 sts. after Rows 224, 226, (227), 228; 1 st. after Rows 230, 232. For SHOULDER bind off 3 sts. after Rows 233, 235, 237.

ROWS 0 to 145: Knit even and make buttonholes after Rows 52, 96, and 140 over the 7th-11th sts. counting from the right side.

Cast on 36 sts, with color 1 and work stockinette st.

Work the left side facing with reverse shapings, casting on from right to left. (Cam Box will be on the LEFT side at Row 0). Omit the buttonholes.

**BE SURE TO NOTIFY US IMMEDIATELY OF ANY CHANGE OF ADDRESS. THE POST OFFICE WILL NOT FORWARD YOUR MAGAZINE TO YOU.**

## DK 8004


SIZE: 6 (Bust 29")  
 YARN: Subita 2 x 3  
 12  
 TENSION: 2 to 4  
 GAUGE: 19 sts, 27 rows  
 22 sts, 27 rows  
 Rib.

10 (Bust 32½")  
 Subita 2 x 3  
 14  
 4 to 6  
 16 sts, 24 rows  
 19 sts, 24 rows

12 (Bust 34")  
 Subita 2 x 3  
 15  
 4 to 6  
 16 sts, 24 rows  
 19 sts, 24 rows

The instructions are the same for all sizes. PATTERN: Stockinette stitch and P3, K1 Ribbing. INCREASES and DECREASES: Full Fashion on stockinette stitch sections and on edges for Ribbed sections. (see Practical Knitting Hints book, pages 14 to 17).

FINISHING: Block all sections. Weave all sections together 1 st. in on each edge, easing in the fullness at bustline of front section. Gather top of sleeve cap, sew sleeve seams and set in. Work 2 rows of single crochet around neck and sleeves.




ROWS 180 to 200: Knit even.

Bring 123 needles into working position and hang the sts. from the stitch holder back onto the machine, increasing 8 sts. evenly across the center 35 stitches in the following manner. Hang 40 sts. onto the machine, pick up a st. from row below. \* Hang 5 sts. onto machine, pick up st. from row below and REPEAT FROM \* 6 x more, then hang the remaining sts. and continue stockinette stitch.

ON EACH SIDE, increase 1 st. after Rows 10, 18, 26, 34, 42, 50, 58, 66, 74, 82, 90, 98, 106, 114, 122, 130, 138, 146, 154, 162, 170. Knit to Row 180, transfer the Ribber stitches to the main machine, then take them off onto a stitch holder. Remove the Ribber.

ROWS 0 to 10: Knit even.

Cast on 73 sts. and work K1, P3 Ribbing.




Move the Cam Box to the left side, transfer the appropriate sts. to the Ribber, turn Row Counter to 140 and complete the left half. Follow the instructions from\*.

ON CAM BOX SIDE, bind off 4 sts. after Rows 206, 208; 5 sts. after Rows 210, 212, 214, 216.

\*ON CAM BOX SIDE, bind off 1 st. after Row 140; 3 sts. after Row 141 (ODD ROWS = NECK SHAPING); 1 st. after Row 142; 3 sts. after Row 143; 1 st. after Row 144; 2 sts. after Rows 145, 147, 149, 151; 1 st. after Rows 152, 153, 155, 157, 159, 160, 161, 165, 168, 169, 173, 176, 184, 192, then knit to Row 206.

ON CAM BOX SIDE, bind off 4 sts. after Rows 126, 127; 3 sts. after Rows 128, 129, 130, 131; 2 sts. after Rows 132, 133, 134, 135, 136, 137; 1 st. after Rows 138, 139. After Row 140, bind off the center 23 sts., put the needles on the left side into holding position (transfer the ribber sts. to main machine first), and complete the right half first.

Knit the front the same as the back to Row 126.



ON EACH SIDE, decrease 1 st. after Rows 76, 100, 124, 148, 172, 196, 220, 244, 268, 292, 300, 308, 316, 324, 332, 340, 348, 356, 364. Knit to Row 376, then bind off the remaining 58 sts. Knit 3 more skirt sections the same.

ROWS 0 to 76: Knit even.

Cast on 96 sts. and work stockinette stitch.

SIZE:	Teen	11/12 (Bust 32")	13/14 (Bust 34")
YARN:	7/8 (Bust 28½")	Subita 2 x 3	Crocus Crepe
50gr. balls	10 C-1	11 C-1	14 C-1
	1 C-2	1 C-2	2 C-2
	1 C-3	1 C-3	1 C-3
TENSION:	3 to 5	4 to 6	5 to 7
GAUGE:	17 sts, 25 rows	16 sts, 24 rows	15 sts, 23 rows

The instructions are the same for all sizes. PATTERN: Stockinette stitch with a Norwegian Design that follows the line drawing or use JAC 40 and PATTERN No. 451. INCREASES and DECREASES: Full Fashion (see KNOTTING Practical Knitting Hints book, pages 14 to 17).

FINISHING: Weave the fronts together, 1 st. in on each edge. Gather lower edge of bodice to measure 15" (16") (17") and join to front of skirt. Join front and back of dress at side seams and shoulders. Sew sleeve seams and set in. Join the Ruffle sections, then gather to measure 39" (41") (43") then sew to bottom of dress. Work 1 row of single crochet around buttons edge of skirt, sleeve edges and neckline. Crochet second row as follows: Ch 5; single crochet into 3rd single crochet; ch 5, single crochet into 6th st. etc. etc. Sew buttons and velvet ribbon to top of dress.

## MK 5329

ON CAM BOX SIDE, bind off 3 sts. after Rows 200, 201; 2 sts. after Rows 202, 203, 204, 205, 206, 207. ON EACH SIDE, decrease 1 st. after Rows 208, 210, 212, 214, 216, 218, 220, 222, 224, 226, 228, 230, 232, 234, 236, 238, 240, 242, 244, 246, 248, 250, 252, 254, 256, 258, 260, 262, 264, 266, 268, 270, 272, 274, 276, 278, 280. ON CAM BOX SIDE, bind off 2 sts. after Rows 282, 283, 284, 285; 3 sts. after Rows 286, 287, 288, 289, then bind off the remaining 11 sts.

ROWS 180 to 200: Knit even.

Bring 123 needles into working position and hang the sts. from the stitch holder back onto the machine, increasing 8 sts. evenly across the center 35 stitches in the following manner. Hang 40 sts. onto the machine, pick up a st. from row below. \* Hang 5 sts. onto machine, pick up st. from row below and REPEAT FROM \* 6 x more, then hang the remaining sts. and continue stockinette stitch.

ON EACH SIDE, increase 1 st. after Rows 10, 18, 26, 34, 42, 50, 58, 66, 74, 82, 90, 98, 106, 114, 122, 130, 138, 146, 154, 162, 170. Knit to Row 180, transfer the Ribber stitches to the main machine, then take them off onto a stitch holder. Remove the Ribber.

ROWS 0 to 10: Knit even.

Cast on 73 sts. and work K1, P3 Ribbing.

Move the Cam Box to the left side, transfer the appropriate sts. to the Ribber, turn Row Counter to 196 and complete the left half. Follow the instructions from\*.


\*Bind off 4 sts. after Row 196 (EVEN ROWS = SHOULDER SHAPING); 6 sts. after Row 197 (ODD ROWS = NECK SHAPING); 4 sts. after Row 198; 6 sts. after Row 199; 5 sts. after Rows 200, 201, 202, 203, 204, 206.

ON CAM BOX SIDE, bind off 4 sts. after Rows 116, 117; 3 sts. after Rows 118, 119, 120, 121; 2 sts. after Rows 122, 123, 124, 125, 126, 127. ON EACH SIDE, decrease 1 st. after Rows 128, 130, 132, 134, 142, 150, 158, 166, 174, 182, then knit to Row 196. Bind off the center 23 sts., put the needles on the left side into holding position and complete the right half first (transfer the ribber sts. to main machine then put the needles into holding position).

ON EACH SIDE, increase 1 st. after Rows 16, 26, 36, 46, 56, 66, 76, 86, 96, 106, then knit to Row 116 (126 on front section).

ROWS 0 to 16: Knit even.

Cast on 155 sts. and work K1, P3 Ribbing.







ruffle - make 3



Cast on 192 sts. and work 78 rows stockinette stitch. Bind off. Make 2 more sections the same.

□ = Color 2 ■ = Color 1 ○ = Color 3



ON EACH SIDE, increase 1 st. after Rows 254, 268, 282, then knit to Row 298 and bind off 131 sts.

ON EACH SIDE, decrease 1 st. after Rows 26, 38, 50, 62, 74, 86, 98, 108, 118, 128, 138, 148, 158, 168, 178, 188, 198, 208, 218, 228, 238. Knit to Row 254.

ROWS 0 to 26: Knit even, then change to stockinette stitch.

Cast on 167 sts. and work the Norwegian Design.


ON CAM BOX SIDE, bind off 3 sts. after Rows 38, 39, 40, 41; 2 sts. after Rows 42, 43, 44, 45, 46, 47; ON EACH SIDE, decrease 1 st. after Rows 48, 50, 52, 54, 56, 58, 60, 62, 64, 66, 68, 70, 72, 74, 76, 78, 80, 82, 84, 86. ON CAM BOX SIDE, bind off 2 sts. after Rows 88, 89; 3 sts. after Rows 90, 91, 92, 93; 4 sts. after Rows 94, 95; After Row 96, bind off the remaining 11 sts.

ROWS 27 to 38: ON EACH SIDE, increase 1 st. after Rows 28, 32, then knit to Row 38.

ON EACH SIDE, increase 1 st. after Rows 4, 8, 12, 16, 20, 24. After Row 26, change to stockinette stitch.

ROWS 0 to 26: Knit even, then change to stockinette stitch.

Cast on 83 sts. and work the Norwegian Design.



Move the Cam Box to the left side, turn the Row Counter back to 408 and complete the left half. Follow the instructions from\*.

\* ON CAM BOX SIDE, bind off 4 sts. after Row 408 (EVEN ROWS = SHOULDER SHAPING); 5 sts. after Row 409 (ODD ROWS = NECK SHAPING); 4 sts. after Row 410; 5 sts. after Row 411; 4 sts. after Rows 412, 413, 414, 415; 5 sts. after Rows 416, 418.


ON CAM BOX SIDE, bind off 3 sts. after Rows 336, 337, 338, 339; 2 sts. after Rows 340, 341, 342, 343; 1 st. after Rows 344, 345, 346, 347, 348, 349, 350, 351. Knit to Row 408, bind off the center 21 sts., put the needles on the left side into holding position and complete the right half first.

ON EACH SIDE, increase 1 st. after Rows 254, 268, 282, 296, 310, 324. Knit to Row 336.

ON EACH SIDE, decrease 1 st. after Rows 26, 38, 50, 62, 74, 86, 98, 108, 118, 128, 138, 148, 158, 168, 178, 188, 198, 208, 218, 228, 238, then knit to Row 254.

ROWS 0 to 26: Knit even, then change to stockinette stitch.

Cast on 167 sts. and work the Norwegian Design.



Make the second bodice front with reverse shapings, casting on from right to left. Cam Box will be on the left side at Row 0.

ON CAM BOX SIDE, bind off 4 sts. after Rows 120, 122, 124, 126; 5 sts. after Rows 128, 130.


ON CAM BOX SIDE, bind off 12 sts. after Row 71; 3 sts. after Rows 73, 75; 2 sts. after Rows 77, 79; 1 st. after Rows 81, 83, 85, 87, 91, 95, 99. Knit to Row 120.

ON CAM BOX SIDE, bind off 3 sts. after Rows 48, 50; 2 sts. after Rows 52, 54; 1 st. after Rows 56, 58, 60, 62, then knit to Row 71.

ON OPPOSITE SIDE OF CAM BOX, decrease 1 st. after Rows in (.). ON CAM BOX SIDE, decrease 1 st. after Rows 10, 16, (16), 22, (24), 28, (32), 34, 40, (40), (48).

ROWS 0 to 10: Cast on 10 sts. after Rows 2, 4, 6, 8 and decrease 1 st. opposite Cam Box after Row 8.

Cast on 39 sts. and work stockinette stitch.



# MK 5330


**SIZE:** 5/6 (Bust 27")  
**YARN:** Subita 2 x 3  
 7 for Dress  
 8 for Slacks  
 Small amount of different colors for trim.  
**TENSION:** 2"  
**GAUGE:** 17 sts, 25 rows

7/8 (Bust 28 1/2")  
 Subita Dralon 3-ply  
 7 for Dress  
 8 for Slacks  
 Small amount of different colors for trim.  
**TENSION:** 2"  
**GAUGE:** 16 sts, 22 rows

9/10 (Bust 30")  
 Subita Dralon 3-ply  
 7 for Dress  
 8 for Slacks  
 Small amount of different colors for trim.  
**TENSION:** 2"  
**GAUGE:** 15 sts, 21 rows

The instructions are the same for all sizes. **PATTERN:** Stockinette stitch with K1, P1 Ribbing at lower edge of sleeves. **INCREASES and DECREASES:** Full Fashion (see **KNITTING Practical Knitting Hints** book, pages 14 to 17).

**FINISHING:** DRESS (or Tunic) Join side seams and shoulders. Sew sleeves together and set in. Work 1 row of single crochet around lower edge, then 1 row of double crochet. Work Row 3 as follows: 1 single crochet into first double crochet; chain 1; 1 double crochet, 3 triple, 1 double crochet into 4th double crochet; chain 1; 1 single crochet into 7th double crochet; chain 1; 1 double crochet, 3 triple, 1 double crochet, 1 double crochet into 10th double crochet, etc. Knit small flowers for trim on front of dress using different colored yarn in the following manner. Cast on 21 sts; put the 1st and every following 4th needle into holding position, knit 8 rows. Return all needles to working position and knit 1 row. Tie ends of yarn together. Take the stitches off onto strand of yarn and pull up to form flowers. Sew flowers to dress as shown in picture and embroider the stems and leaves as illustrated. Pull a twisted cord through double crochet at neckline. **PANTS:** Join front and back and leg seams. Turn upper edge in half to form hem and sew. Insert elastic at waistline. Make hem at lower edge of legs.




Work the second section with reverse shapings, casting on from right to left. Cam Box will be on the left side at Row 0.

**ON OPPOSITE SIDE OF CAM BOX,** put 50 needles into holding position after Row 382, 15 needles after Rows 384, 386, 388. After Row 390, bring all the needles into working position and knit even to Row 412. Bind off 121 sts.

**ON CAM BOX SIDE,** bind off 3 sts, after Row 281; 4 sts, after Row 282; 3 sts, after Row 283; 4 sts, after Row 284; 2 sts, after Row 285; 3 sts, after Row 286; 2 sts, after Row 287; 3 sts, after Row 288; 1 st, after Row 289; 2 sts, after Row 290; 1 st, after Row 291; 2 sts, after Row 292; 1 st, after Row 293; 2 sts, after Row 294; 1 st, after Rows 296, 297, 298, 300, 301, 302, 306, 307, 310, 313, 314, 322, 330, 338, 346, 354, 362, 370, 378. Knit to Row 382, then knit short rows.

**ON CAM BOX SIDE,** increase 1 st, after Rows 156, 157, 164, 167, 172, 177, 180, 187, 188, 196, 197, 204, 207, 210, 216, 217, 222, 227, 228, 234, 237, 240, 246, 247, 252, 257, 258, 264, 267, 270, 276, 277, then knit to Row 281.


**ROWS 0 to 156:** Knit even.  
 Cast on 140 sts, and work stockinette stitch.



**ON CAM BOX SIDE,** bind off 5 sts, after Row 295 (ODD ROWS = NECK SHAPING); 3 sts, after Rows 297, 299; 2 sts, after Rows 301, 303; 1 st, after Rows 305, 307; 3 sts, after Row 308 (EVEN ROWS = SHOULDER SHAPING); 1 st, after Row 309; 4 sts, after Row 310; 1 st, after Row 311; 4 sts, after Rows 312, 314, 316, 318, 320, 322.

**ON CAM BOX SIDE,** bind off 3 sts, after Rows 234, 236; 2 sts, after Rows 238, 240; 1 st, after Rows 242, 244, 246, 248, then knit to Row 294.

The front is worked the same as the back to Row 234, then put 64 needles on the left side into holding position and complete the right half first.



Move the Cam Box to the left side, turn the Row Counter back to 308 and complete the left half. Follow the instructions from\*.

**\*ON CAM BOX SIDE,** bind off 3 sts, after Row 308 (EVEN ROWS = SHOULDER SHAPING); 3 sts, after Row 309 (ODD ROWS = NECK SHAPING); 4 sts, after Row 310; 3 sts, after Row 311; 4 sts, after Row 312; 2 sts, after Row 313; 4 sts, after Row 314; 2 sts, after Row 315; 4 sts, after Row 316; 2 sts, after Row 317; 4 sts, after Row 318; 2 sts, after Row 319; 4 sts, after Rows 320, 322.

**ON CAM BOX SIDE,** bind off 3 sts, after Rows 234, 235, 236, 237; 2 sts, after Rows 238, 239, 240, 241; 1 st, after Rows 242, 243, 244, 245, 246, 247, 248, 249. Knit to Row 308, bind off the center 10 sts., put the needles on the left side into holding position and complete the right half first.

**ON EACH SIDE,** decrease 1 st, after Rows 26, 38, 50, 62, 74, 84, 94, 104, 114, 124, 134, 144, 154, 164, then knit to Row 234.


**ROWS 0 to 26:** Knit even.  
 Cast on 156 sts, and work stockinette stitch.

**ON CAM BOX SIDE,** bind off 4 sts, after Rows 188; 3 sts, after Rows 190, 191, 192, 193; 2 sts, after Rows 194, 195. **ON EACH SIDE,** decrease 1 st, after Rows 196, 198, 200, 202, 204, 206, 208, 210, 212, 214, 216, 218, 220, 222, 224, 226, 228, 230, 232. **ON CAM BOX SIDE,** bind off 2 sts, after Rows 234, 235; 3 sts, after Rows 236, 237, 238, 239; after Rows 240, bind off the remaining 11 sts.

**ON EACH SIDE,** INCREASE 1 st, after Rows 80, 98, 116, 134, 152, 170, then knit to Row 188.  
**ROWS 60 to 80:** Knit even.

Bring 77 needles into working position and hang the sts, from the stitch holder onto these needles, increasing 16 sts across by picking up a stitch from the row below after the 1st and every 4th stitch. Turn Row Counter to 60 and continue in stockinette stitch.

**ROWS 0 to 60:** Knit even, then transfer the ribber sts, to main machine and take the sts, off onto a stitch holder. Continue in stockinette stitch.  
 Cast on 61 st, and work K1, P1 Ribbing.



Move the Cam Box to the left side, turn the Row Counter back to 234 and complete the left half. Follow the instructions from\*.

**ON CAM BOX SIDE,** bind off 5 sts, after Row 295 (ODD ROWS = NECK SHAPING); 3 sts, after Rows 297, 299; 2 sts, after Rows 301, 303; 1 st, after Rows 305, 307; 3 sts, after Row 308 (EVEN ROWS = SHOULDER SHAPING); 1 st, after Row 309; 4 sts, after Row 310; 1 st, after Row 311; 4 sts, after Rows 312, 314, 316, 318, 320, 322.

**ON CAM BOX SIDE,** bind off 3 sts, after Rows 234, 236; 2 sts, after Rows 238, 240; 1 st, after Rows 242, 244, 246, 248, then knit to Row 294.



The front is worked the same as the back to Row 234, then put 64 needles on the left side into holding position and complete the right half first.

# HP 3656

**SIZE:** 36 (Chest 36"-37") 38 (Chest 38"-39") 42 (Chest 42"-43")  
**YARN:** Sonika Dralon  
**50gr. balls** 11 11 14  
**TENSION:** 6 to 8 7 to 9 9 or 10  
**GAUGE:** 2" 14 sts, 22 rows 13 sts, 21 rows 12 sts, 19 rows

The instructions are the same for all sizes. **PATTERN:** Stockinette stitch with Pattern Design on the front section. Follow the Line Drawing. The Design is worked over 30 center needles. Transfer the appropriate sts, as shown in the Drawing. After 20 or 30 rows, drop the appropriate stitches and latch them up into knit stitches. **NECK DECREASES:** Hang the 18th st. (counting from the center) onto the 17th st., then move the sts. over to fill the empty needles. **SLEEVE INCREASES:** Full Fashion (see **KNITTING Practical Knitting Hints book**, pages 14 to 17).

**FINISHING:** Block all sections. Join front to back at sides and shoulders. Sew sleeves together and set in. Weave the two short ends of Neckband together then sew to neckline.



Bring the Cam Box to the left side, turn the Row Counter back to 190 and complete the left half. Follow the instructions from\*.

**ON CAM BOX SIDE:** bind off 3 sts. after Rows 282, 284; 4 sts. after Rows 286, 288, 290, 292, 294, 296, 298.

Continue to shape V after Rows 212, 217, 222, 227, 232, 237, 242, 247, 252, 257, 262, 267, 272, 277, 282.



\*Continue to shape V Neckline on Rows in ( ), transferring the 18th st. to the 17th needle and move the sts. over and **ON CAM BOX SIDE,** bind off 4 sts. after Rows 190, 192, (192); 2 sts. after Rows 194, 196, (197), 1 st. after Rows 198, 200, 202, (202), 204, (207).

Always counting from the center of your pattern, transfer the 18th st. **ON EACH SIDE,** to the 17th st. and move the sts. over to fill the empty needles after Rows 182, 187. After Row 190, hang the 2 center sts., one to the neighboring needle on the right and one to the neighboring needle on the left. Put all the needles on the left side into holding position and complete the right half first.

**ROWS 31 to 182:** Knit even.


**ROWS 0 to 30:** Knit even, then change to stockinette stitch and begin the Pattern Design. After 20 or 30 rows, drop the appropriate sts. and latch up into knit sts.

Cast on 140 sts. and work K1, P1 Ribbing.



**ROWS 0 to 18:** **ON EACH SIDE,** bind off 2 sts. after Rows 2, 4, 6, 8, 10, 12, 14. To make a 2 st. bind off, transfer the end Ribber stitch to the main machine. Now place the 2nd st. on the main machine onto the 3rd needle behind the latch, transfer the 1st st. to the 3rd needle, pull this stitch through the 2 sts. on the needle. After Row 18, bind off the crochet method for Ribbing.

Cast on 195 sts. and work K1, P1 Ribbing.



Bring the Cam Box to the left side, turn the Row Counter back to 286 and complete the left half. Follow the instructions from\*.

\***ON CAM BOX SIDE,** bind off 4 sts. after Row 286 (EVEN ROWS = SHOULDERS SHAPING); 5 sts. after Row 287 (ODD ROWS = NECK SHAPING); 4 sts. after Row 288; 5 sts. after Row 289; 4 sts. after Row 290; 3 sts. after Row 291; 4 sts. after Rows 292, 294, 296, 298.

**ON CAM BOX SIDE,** bind off 3 sts. after Rows 282, 284. After Row 286, bind off the center 14 sts., put the needles on the left side into holding position and complete the right half first.

**ON CAM BOX SIDE,** bind off 4 sts. after Rows 190, 191, 192, 193; 2 sts. after Rows 194, 195, 196, 197; 1 st. after Rows 197, 198, 199, 200, 201, 202, 203, 204, then knit to Row 282.

**ROWS 31 to 190:** Knit even.

**ROWS 0 to 30:** Knit even, then change to stockinette stitch.

Cast on 140 sts. and work K1, P1 Ribbing.










# KK 5299

- SIZE:** 2 (Chest 21") 3 (Chest 22") 4 (Chest 23")  
**YARN:** Fortissima Fortissima Fortissima  
 50gr. balls 4 for Pullover 4 for Pullover 4 for Pullover  
 4 for Pants 4 for Pants 4 for Pants  
**TENSION:** 3 to 5 17 sts, 23 rows 16 sts, 22 rows  
**GAUGE:** 2" 18 sts, 25 rows 16 sts, 22 rows

The instructions are the same for all sizes. **PATTERN:** Stockinette stitch with Cable design down center front of Pullover. After 30 or 40 rows, drop the 50th st. on each side and latch up into a knit stitch. 1 x 1 Ribbing for bands, **INCREASES and DECREASES:** Full Fashion (see Practical Knitting Hints book, pages 14 to 17).

**FINISHING:** Block all sections. **PULLOVER:** Join front to back at side seams. Sew right shoulder seam and sew left shoulder for 3/4". Turn edges of opening narrowly to inside and sew. Sew sleeve seams and set in. Fold neckband in half and sew one edge to inside and one to outside of neckline. Make 4 loops and sew on buttons. **PANTS:** Join side seams then join front and back center seams. Make a 2" hem on legs. Make hem at waist and insert elastic.




**ON CAM BOX SIDE, bind off 3 sts.** after Rows 116, 117, 118, 119; 2 sts. after Rows 120, 121, 122, 123, 124, 125; **ON EACH SIDE, decrease 1 st.** after Rows 126, 128, 130, 132, 134, 136, 138, 140, 142, 144, 146. **ON CAM BOX SIDE, bind off 2 sts.** after Rows 148, 149, 150, 151; 3 sts. after Rows 152, 153, 154, 155. After Row 156, bind off 11 sts.

**ON EACH SIDE, increase 1 st.** after Rows 16, 26, 36, 46, 56, 66, 76, 86, 96, 106. Knit to Row 116.

**ROWS 0 to 16:** Knit even, then change to stockinette stitch.

Cast on 57 sts. and work K1, P1 Ribbing.



Cast on 101 sts. and work 20 rows K1, P1 Ribbing, then bind off the crochet method for Ribbing.

Make the second section with reverse shaping, casting on from right to left. Cam Box will be on the left side at Row 0.

**ROWS 250 to 300:** Knit even, then bind off 72 sts.


**ON EACH SIDE, decrease 1 st.** after Rows 120, 124, 128, 132, 136, 140, 144, 148, 152, 156, 160, 164, 168, 172, 176, 182, 188, 194, 200, 206, 212, 218, 224, 230, 236, 242, 248.

**ON EACH SIDE, increase 1 st.** after Rows 90, 94, 98, 102, 106, 108, 110, 112, 114, 116, 118.

**ON OPPOSITE SIDE OF CAM BOX, put 86 needles into holding position after Row 24. ON OPPOSITE SIDE OF CAM BOX, bring back into working position, 15 needles after Rows 26, 28, 30, 32, and 26 sts. after Row 34 then knit to Row 90.**

**ROWS 0 to 24:** Knit even, then work short rows.

Cast on 104 sts. and work stockinette stitch.



Make the second front section with reverse shaping.

**ON CAM BOX SIDE, bind off 2 sts.** after Row 370, 372, 374, 376, 378, 380, 382, 384, 386, 388.

**ON CAM BOX SIDE, bind off 7 sts.** after Row 333 (ODD ROWS = NECK SHAPING); 4 sts. after Rows 337, 341; 2 sts. after Rows 345, 349; 1 st. after Rows 353, 357 then knit to Row 370.

**ON CAM BOX SIDE, bind off 3 sts.** after Rows 242, 246; 2 sts. after Rows 250, 254; 1 st. after Rows 258, 262, then knit to Row 333.

**ROWS 13 to 242:** Knit even.

**ROWS 0 to 12:** Knit even, then cast on 10 sts. on the left side (use separate strand of yarn for casting on). After Row 12, change to Holding Position Design.

Cast on 41 sts. and work stockinette stitch.

Move the Cam Box to the left side, turn the Row Counter back to 370 and complete the left half. Follow the instructions from\*.




\***ON CAM BOX SIDE, bind off 2 sts.** after Row 370 (EVEN ROWS = SHOULDER SHAPING); 2 sts. after Rows 371 (ODD ROWS = NECK SHAPING); 2 sts. after Rows 372, 373, 374, 375, 376; 1 st. after Row 377; 2 sts. after Row 378; 1 st. after Row 379; 2 sts. after Row 380; 1 st. after Row 381; 2 sts. after Row 382; 1 st. after Row 383; 2 sts. after Rows 384, 386, 388.

**ON CAM BOX SIDE, bind off 3 sts.** after Rows 242, 243, 246, 247; 2 sts. after Rows 250, 251, 254, 255; 1 st. after Rows 258, 259, 262, 263. Knit to Row 370. Bind off the center 9 sts., put the needles on the left side into holding position and complete the right half first.

**ROWS 13 to 242:** Knit even.

**ROWS 0 to 12:** Knit even, then begin the holding position design.

Cast on 93 sts. and work stockinette stitch.



**ON CAM BOX SIDE, bind off 2 sts.** after Rows 378, 379, 382, 383; 3 sts. after Rows 386, 387, after Row 388, bind off the remaining 7 sts.

**ON CAM BOX SIDE, bind off 3 sts.** after Rows 306, 307; 2 sts. after Rows 310, 311, 314, 315, 318, 319. **ON EACH SIDE, decrease 1 st.** after Rows 322, 326, 330, 334, 338, 342, 346, 350, 354, 358, 362, 366, 370, 374.

**ON EACH SIDE, increase 1 st.** after Rows 30, 62, 94, 126, 158, 190, 222, 250, 278, then knit to Row 306.


**ROWS 0 to 30:** Knit even, then change to Holding Position Design.

Cast on 49 sts. and work Fisherman's Rib (Put the Gate Cam Release Lever of the Ribber to the Needle Heels).

# KG 1935

SCARF

**YARN:** 5-50gr. balls Subita Dralon 2-ply. **TENSION:** 4 to 6. **GAUGE:** 19 sts, 38 rows = 2".  
**PATTERN:** Fisherman's Rib with the Gate Cam Release Lever of the Main Machine to the Needle Heels and the Gate Cam Release Lever of the Ribber to the Needle Heads  
**FINISHING:** Cut fringe by winding yarn around a 6" cardboard and cut one side. Using 6 strands of yarn, knot fringe along each end of Scarf.




Cast on 121 sts. and work Fisherman's Rib. After Row 1020, bind off all sts.

# KG 1934

SCARF

**YARN:** 4-50gr. balls color 1, and 4-50gr. balls color 2. Subita Dralon 2-ply. **TENSION:** 3 to 5. **GAUGE:** 28 sts, 24 rows = 2". **PATTERN:** 1 x 1 Ribbing with stripes.  
**FINISHING:** Cut fringe by winding yarn around 6" cardboard and cut only 1 side. Using 6 strands of yarn, knot fringe along each end of Scarf.



Cast on 169 sts. and work K1, P1 Ribbing with stripes of 60 rows color 1 and 60 rows color 2. After Row 1040, bind off all sts.

Move the Cam Box to the left side, turn the Row Counter back to 152 and complete the left half. Follow the instructions from\*.

ON CAM BOX SIDE, bind off 4 sts. after Rows 168, 170, 172, 174, 176; 5 sts. after Row 178.


\*ON CAM BOX SIDE, bind off 3 sts. after Rows 153, 155; 2 sts. after Rows 157, 159; 1 st. after Rows 161, 163, 165. Knit to Row 168.

ON CAM BOX SIDE, bind off 3 sts. after Rows 112, 113; 2 sts. after Rows 114, 115, 116, 117. ON EACH SIDE, decrease 1 st. after Rows 118, 120, 122, 124, then knit to Row 152. Bind off the center 10 sts., put the needles on the left side into holding position and complete the right half first.

ROWS 17 to 112: Knit even.

ROWS 0 to 16: Knit even, then continue in stockinette stitch with Pattern design worked over the center 10 needles.

Cast on 108 sts. and work K1, P1 Ribbing.



Move the Cam Box to the left side, turn the Row Counter back to 168 and complete the left half. Follow the instructions from\*.


\*ON CAM BOX SIDE, bind off 4 sts. after Rows 168 (EVEN ROWS = SHOULDER SHAPING); 4 sts. after Row 169 (ODD ROWS = NECK SHAPING); 4 sts. after Rows 170, 171, 172; 2 sts. after Row 173; 4 sts. after Row 174; 2 sts. after Row 175; 4 sts. after Row 176; 5 sts. after Row 178.

ON CAM BOX SIDE, bind off 3 sts. after Rows 112, 113; 2 sts. after Rows 114, 115, 116, 117; 1 st. after Rows 118, 119, 120, 121, 122, 123, 124, 125, then knit to Row 168. Bind off the center 12 sts., put the needles on the left side into holding position and complete the right half first.

ROWS 17 to 112: Knit even.

ROWS 0 to 16: Knit even, then continue in stockinette stitch.

Cast on 108 sts. and work K1, P1 Ribbing.



Cast on 65 sts. OVER EVERY 3rd NEEDLE. Rows 1 to 20: Knit in stockinette stitch. Rows 21 to 108: Knit in Pattern. Rows 109 to 112: Knit in stockinette stitch, then take the sts. off onto stitch holder. Hang the sts. back onto 43 needles by putting 2 sts. on needles 1, 3, 7, 9, etc. Rows 113 to 118: Knit in stockinette stitch. Drop needles 2, 4, 6, 8, etc. down 8 rows and latch up into a knit stitch. Take the purl sts. then the knit sts. off onto separate strands of yarn.


# KG 1937

HAT

**YARN:** 3-50gr. balls Frigate or Leacril. **TENSION:** 5 to 8 over EVERY 3rd NEEDLE. **GAUGE:** 7 sts., 26 rows = 2" in pattern stitch.

**PATTERN:** \*Put the 2nd and every other needle into holding position and knit 2 rows. Return the needles to working position. Put the 1st, then every other needle into holding position and knit 2 rows. REPEAT from \* for Pattern. **KNITTING machine owners, use the NEEDLE SHIFTER.**

**FINISHING:** Weave the long seam. Pull up the sts. held on strands of yarn and tie securely. Turn up 10 rows at lower edge and hem to outside. Fold up hem section.



## KG 1938

**BABY CAR BED COVER, KIDDIE CAR COAT with BOOTIES**  
YARN: 3-50gr. balls for Car Bed Cover; 2-50gr. balls for Car Coat and Booties, KNITTING Subita Dralon 2-ply. TENSION: 7 to 9. GAUGE: 12 sts., 3 rows = 2" in Pattern stitch.

**PATTERN STITCH:** \*Push the 4th and every following 4th needle into holding position. Knit 4 rows. Push the 2nd and every following 4th needle into holding position. Knit 4 rows. \*REPEAT from \* to \* for Pattern. KNITTING machine owners use Wheel No. 3. Push in the left Retractor Button before knitting the 4th row, then release button before knitting the next row.

**FINISHING: CAR BED COVER:** Make 1 row of single crochet around all edges, then 1 row of shell stitch as follows: \*3 double crochet, 2 treble crochet, 3 double crochet in first single of shell stitch, skip 3 single crochet, 1 single crochet in next st. Skip 3 single crochet and REPEAT from \* around. **CAR COAT:** Seam top of Hood, sides and sleeves. Make 1 row of single crochet around all edges, then 1 row of Shell stitch as follows: \*Chain 3, 3 double crochet in same place at base of chain. Skip 3 sts., 1 single crochet in next stitch\*. This makes 1 shell. REPEAT from \* to \*. **BOOTIES:** Weave the sts, held on contrast yarn and remove contrast. Sew up side seams. Press lightly.

### KIDDIE CAR COAT

Cast on 73 sts. Knit 2 rows. Begin Pattern Stitch and continue in pattern till counter reads 98.


First put needles into position to make pattern, then cast on 36 sts, for sleeve (right side of machine). Be sure to place the stitches behind the latches. Leave the newly cast on sts. in working position and knit 1 row. Cast on the same number of sts. on the left side of machine, leave in working position and knit 1 row.

Now put the required needles on both sides in holding position to make pattern all across the next two rows. Continue in pattern stitch until counter reads 158. **ON EACH SIDE OF CENTER NEEDLE** return 4 holding position needles to working position. Knit 1 row. Put 27 sts. in the center of garment onto a stitch holder. Put needles on right side into holding position. Continue knitting pattern on the left side only for 3 rows. Cam Box is now on the right side. Cast on 18 sts. (putting them behind the latches) for neck.

Set Counter at 0. Continue in pattern on the left side of garment for 66 rows.

Counting from the left, put first 9 needles that are in holding position back into working position and knit 1 row. On the left side, bind off 36 sts. and continue working in pattern until Counter reads 164. Return all needles to working position and knit 2 rows. Bind off loosely.

**FOR RIGHT SIDE OF COAT,** have the Cam Box at left of work, attach yarn at left and put needles in proper position to continue pattern as before moving needles into holding position, knit 3 rows. Counter at 0.




## KG 1936

**BAG with the LOOK OF CROCHET**

YARN: 5-50gr. balls Leacril. 1/2 yard material for lining. 1 package beads in multi-color with large holes. 9" zipper for pocket. GAUGE: 7 sts., 19 rows = 2" measured over Pattern.

**PATTERN STITCH:** Knitted OVER EVERY 3rd NEEDLE. \*Put the 2nd, then every other needle into Holding Position, knit 2 rows. Return these needles to working position. Put the 1st, then every other needle into holding position and knit 2 rows. Return these needles to working position and REPEAT from \* 1 x more (8 rows). All needles in work, knit 2 rows. **KNITTING machine owners,** use your Needle Shifter from right to left to shift the pattern and from left to right to bring all the needles into work to knit the 9th and 10th row of pattern. REPEAT from first \* for pattern.

**FINISHING:** Cut matching lining for bag, using the bag as a pattern, but omit lining the flap. Make a 9" pocket for one side and a 9" plain pocket for other side. Attach to lining then sew side seams of lining. Fold bag so that the cast-on edge meets the marked edges. Pin carefully matching the patterns on each side. Single crochet sides together, across opening and around flap and lower edge, then make 1 row of reverse single crochet over first row with a chain 5 at point of flap (be sure it will go over button of your choice). Pin and then sew in lining. Sew cord across flap on the inside. Sew on button. Make fringe by winding yarn around a 12" cardboard and cut only 1 side. Using 6 strands of yarn, tie fringe across lower edge of bag. Tie beads into fringe in a hit or miss pattern and sew some beads onto a crochet button. Trim fringe evenly.



Cast on 39 sts. over EVERY 3rd NEEDLE. Knit 2 rows stockinette stitch then put Counter at 0. Knit in Pattern to Row 200. Mark each side with a bit of contrast yarn, then knit in Pattern to Row 220.

**ON EACH SIDE,** decrease 1 st. and REPEAT the decreases on EVERY ROW 17 x more. When making the decreases, shift the needles, then transfer the end st. **ON EACH SIDE** to the next needle and knit this stitch off with the transfer and stitch, then continue with pattern. After Row 240, bind off the remaining 3 sts.

Continue in pattern and on the 4th row, at neck edge, cast on 18 sts. Be sure to put the stitches behind the latches. Knit in pattern for 66 rows.

Beginning at right, return 9 needles now in holding position to working position and knit 2 rows. From right side, bind off 36 sts. Continue in pattern to row 166. Return all needles to working position and knit 2 rows. Bind off loosely.

**HOOD:** Cam Box on the left side of machine. With purl side of garment facing you, pick up 28 sts. on the right, 27 sts. from stitch holder, and 28 sts. on the left (83 sts. in all). Attach yarn on the left side and knit 1 row. Beginning from the right side, put stitch No. 2 on needle No. 3 (behind the latch), stitch No. 4 on No. 5, etc. across row. Leave empty needles in the out of work position. Knit across. Return the empty needles to working position and knit 1 row.

Row Counter at 0. Proceed with Pattern stitch for 92 rows. Return all needles to working position and knit 2 rows. Bind off loosely.

**BOOTIES:** Tension 6 for Pattern Stitch; Tension 4 for Stockinette Stitch. Cast on 43 sts. Tension 6. Knit in pattern for 60 rows. Increase 1 st. (44 sts.). Change to Tension 4 and stockinette stitch. Knit 4 rows. Transfer the 3rd st. to 4th, 5th to 6th, etc. across the row. Leave all needles in working position. Knit 4 rows. Put 22 sts. on the left side into Holding position. Put 1 needle opposite Cam Box beginning every row till 6 remain in work. (Be sure to wrap the yarn around the inside needle in holding position.) Put 1 needle back at a time till 22 are in work. Put all the needles on the left into working position and knit 18 rows over all needles. On the right side, put 22 needles in holding position and work toe same as the heel on the left side. Take off on contrast yarn. Make 2nd Bootie with reverse shaping.

### BABY CAR BED COVER

Cast on 193 sts. Knit 2 rows. Counter at 0. Knit in Pattern. Stitch till counter reads 472. All needles in working position, knit 2 rows. Bind off loosely.



# knitking

*Offers Complete Service To The Machine Knitter . . .*



**KNITKING KNITTING MACHINES** — The finest and most versatile automatic knitters available anywhere in the world — KNITKING is the worlds most honored machine with five gold medals for excellence. KNITKING Push-Button knitters produce a range of patterns and knit a variety of yarns unequalled by other machines.

**KNITKING MAGAZINE** — Without a doubt the finest Knitting machine magazine in the English language published anywhere in the world. Twenty original patterns in each issue and for all members of the family. Stylish designs photographed on world famous models. High fashion garments, handsome sweaters, sports outfits, baby clothes, plus accessories and knitting machine hints. All available to you in KNITKING MAGAZINE.

**KNITKING YARNS** — We searched the world over for the finest yarns obtainable and one look inside our catalogue will prove that we found them. A complete range of beautiful crepe machine washable 100% wool yarns . . . luxurious mohairs . . . handsome tweeds . . . pretty mixtures and luscious synthetics that are machine washable . . . easy to care for . . . and yet, can be knitted into the most glamorous of garments.

If you want your garments to look as good as those in KNITKING MAGAZINE and keep their appearance through dozens of washes, you must knit them with gorgeous KNITKING yarns. KNITKING yarns are the finest quality obtainable anywhere and the prices cannot be beaten. Try them once and you will always use them.

Send \$1.00 for LARGE COMPLETE YARN CATALOGUE  
(Refunded on your first \$10.00 order) to:

KNITKING YARNS, Dept. 19  
1128 Crenshaw Boulevard  
Los Angeles, California 90019



# KNITTING NEWS

January/February, 1972

## OUR READERS WRITE

Many readers have written asking that we again include the prices of KNITTING YARNS for all the patterns in each issue of KNITTING MAGAZINE.... The complete list and prices for the various sizes in this issue is included at the end of this Newsletter... At first glance, you could be confused by variations in prices... Sometimes, the yarn for a large size can cost less than that for a small size... This, of course, is because a different type of yarn is used for different sizes.

We have also received letters from readers telling us that they can obtain yarns at lower prices than ours... We know you can, but you cannot obtain yarns of KNITTING quality at lower prices than ours... Cheap yarns usually result in cheap looking garments... When for just a little more, you can have garments of the quality shown within the pages of this magazine... Take the Cover garment of this issue as an example.. To make the Blazer, Skirt and Vest in a size 12, using beautiful KNITTING YARNS costs \$38.27... You could not buy anything comparable in a custom knit shop for under \$200.00... By using a cheaper yarn, you could conceivably save as much as \$20.00 of the \$38.27, but it is very unlikely that the finished garment would have the look of Quality and Class depicted on our Front Cover... There is an old Maxim that certainly applies in knitting... It is ... "THE BEST IS ALWAYS CHEAPEST".. Buy top quality KNITTING YARNS and be sure of the best.

## CHILDRENS BOOK

We are completely sold out of the Childrens Book and are not considering a reprint at this time... A pattern book of any sort becomes dated if it is around for too long and as we regularly include up to date childrens patterns in KNITTING MAGAZINE we believe that we can satisfy the need without a separate publication. If there is any particular type of childrens patterns you would like to see included in KNITTING MAGAZINE, please drop us a line... We will not be able to satisfy individual needs, but if we have several requests for a specific item, we will certainly do our best to provide it.

## THE MORIARTY SKI HAT

There is a fascinating story in the January 1972 edition of Ladies Circle Magazine about the world famous Moriarty Ski Hat... It seems that its design came about by accident. Mrs. Moriarty was making a hat for her son, an Olympic Skier. She was new to knitting machines and the top of the hat came out a different shape than was intended. Her son wore it anyway, with the result that other skiers intrigued with its shape as well as its efficiency, wanted to obtain similar hats... She made them for them and the business just grew and grew to where today fifty people are working in their own homes making the Moriarty hats and using forty thousand pounds of top quality wool a year... Mrs. Moriarty soon discovered that nothing but the best quality wool provided the built in stretch needed for Ski Hats and that hats made with cheap wool did not retain their shape.

We are happy that the Moriarty's chose KNITTING machines for making their hats... KNITTING was chosen because of its ability to knit worsted weight yarns on every needle.

## PRACTICAL KNITTING HINTS

DK 7995: The Popcorn Pattern for this lovely Suit is easy to knit if you work with 2 balls of the main color yarn. If you have a KNITTING machine, the Adjustable Needle Selector can be used for setting the needles into pattern. When you begin, knit 4 rows with main color yarn over all the needles. Set up the pattern and with contrast yarn, knit 3 rows (KNITTING Machine owners, push in the RIGHT Retractor Button before knitting the 3rd row, knit 1 row then release the button). Your Cam Box is now on the LEFT SIDE, so take a second ball of main color yarn and knit 4 rows over all the needles. Set up the pattern, knit 3 rows with the contrast yarn (KNITTING Machine owners, push in the LEFT Retractor Button before knitting the 3rd row, knit 1 row then release the button). Your Cam Box is now on the RIGHT SIDE and you are ready to knit 4 rows using the first ball of main color yarn. It is best to hand feed the yarns for this pattern, but be sure to practice on a sample piece first and hold the yarn rather firmly across the needles and allow it to run smoothly through your fingers as you push the Cam Box across the needle bed.

MK 5330: After knitting the cuff section of the sleeves, you must first transfer the Ribber sts. to the Main Machine, then take the sts. off onto a stitch holder. We like to use contrast waste yarn for a stitch holder, so we knit 6 to 8 rows using the waste yarn, then slide the Cam Box across the machine without yarn so that the stitches will drop off. Now you will replace the stitches held on contrast yarn onto 77 needles, increasing 16 sts. evenly across the knitting.... Bring 77 needles into working position and counting from the right edge, bring the 2nd, then every 5th needle into holding position. The 16 needles in holding position are your increase needles. As you hang the sts. held on contrast yarn, you must pick up a stitch from the row below to hang onto each increase needle. When you have hung all the sts., be sure all the needles are in working position, turn your Row Counter to 60 and continue in Stockinette stitch.

## QUESTIONNAIRE

As regular readers know we include a questionnaire with every subscription renewal form sent to subscribers... the information obtained from these questionnaires helps us determine what to include in future issues of KNITTING MAGAZINE...

We analyze these completed questionnaires regularly, and have noticed recently a repetition of many requests for such things as... How to put Seams together... How to put on Neck Bands... How to make Buttonholes... How to make Pom-poms and Knitted Cords... How to Block Garments... How to make Raglan Patterns... How to do Full Fashioning etc., etc....

The answers to all these questions and many many

more are contained in the pages of our wonderful little book "Practical Knitting Hints"... If you own a knitting machine (irrespective of brand), you will find 'Practical Knitting Hints' indispensable... It only costs \$2.95 (California residents add 15¢ Sales Tax) plus 40¢ mailing costs.

BACKGROUND to PICTURES

We know that we will get letters asking about the background to the pictures in this issue...so we will tell you that it is a photo of a part of Los Angeles with the Hollywood Hills in the background ... taken on a rare day when the Wind blew the Smog away and beautiful puffy Clouds filled the Sky.....

NUMBER		SIZE	COST	SHIP- ING
DK 8065	Woman's Blazer, Skirt & Vest	10	\$38.40	\$1.70
		12	38.27	2.05
		14	42.72	2.05
DP 8066	Woman's Pullover	10	8.40	1.00
		12	8.40	1.00
		14	9.60	1.00
DK 8059	Woman's Jacket & Hot Pants	8	16.80	1.00
		10	24.00	1.00
		12	23.14	1.35
DK 8060	Woman's Pullover & Leotites	8	15.60	1.00
		10	24.00	1.00
		12	24.00	1.00
DP 8000	Woman's Pullover	10	7.92	1.00
		14	9.90	1.00
		16	12.00	1.00
DK 7995	Woman's Suit	10	22.80	1.00
		14	34.27	1.35
		18	25.20	1.35
DK 8004	Woman's Dress	6	14.40	1.00
		10	16.80	1.00
		12	18.00	1.00

NUMBER		SIZE	COST	SHIP- ING
KK 5306	Boy's Jacket & Hat	4	\$ 8.40	\$1.00
		6	12.00	1.00
		8	13.20	1.00
KK 5299	Child's Pullover & Pants	2	6.93	1.00
		3	7.92	1.00
		4	7.92	1.00
KG 1934	Scarf		9.60	1.00
KG 1935	Scarf		6.00	1.00
KG 1937	Woman's Hat	Frigate	2.37	1.00
		Leacril	2.67	1.00
KG 1936	Bag with look of Crochet		4.45	1.00
KG 1938	Baby Car Bed Cover, Kiddie Car Coat & Booties		6.00	1.00
HP 3656	Man's Pullover	36	13.20	1.00
		38	13.20	1.00
		42	12.46	1.00
HP 3654	Man's Pullover & Slacks	36	22.80	1.00
		38	22.80	1.00
		40	22.80	1.00
MK 5300	Girl's Coat, Cap, Scarf & Mittens	3/4	12.00	1.00
		5/6	12.00	1.00
		8/9	14.40	1.00
MK 5329	Girl's Dress (teen)	7/8	14.40	1.00
		11/12	15.60	1.00
		13/14	20.40	1.00
MK 5330	Girl's Dress (or Tunic) & Slacks (teen)	5/6	16.80	1.00
		7/8	18.00	1.00
		9/10	18.00	1.00

\* \* \* \* \*

**ARE YOU UNHAPPY WITH  
YOUR PRESENT KNITTING MACHINE ?**

**DOES IT REFUSE TO KNIT FANCY DRESS YARNS?**

**DOES IT JAM UP WHEN YOU TRY TO KNIT LOOPED MOHAIR OR THICK AND THIN YARNS?**

**DOES IT DROP STITCHES ALL OVER THE PLACE?**

**ARE YOU CONTINUALLY HAVING TROUBLE WITH AWKWARD, CUMBERSOME WEIGHTS?**

**ARE YOU UNABLE TO MAKE A LARGE GARMENT WITH BULKY YARNS?**

**DO YOU HAVE TO SELECT PATTERN STITCHES MANUALLY?**

**DO YOU HAVE TO LATCH YOUR RIBBING BY HAND?**

**IF YOU ARE HAVING ANY OF THESE PROBLEMS YOU SHOULD TRADE UP TO A NEW FANTASTIC PUSH BUTTON KNITTING WITH COORDINATED RIBBER AND ENJOY KNITTING WITH THE WORLDS FINEST, MOST VERSATILE AND MOST AUTOMATIC KNITTER.**

**YOU WILL BE SURPRISED AT OUR GENEROUS TRADE-IN ALLOWANCE AND YOU CAN, IF YOU WISH, USE YOUR PRESENT MACHINE AS A DOWN-PAYMENT AND PURCHASE A COMPLETE KNITTING FOR JUST PENNIES A DAY. WRITE TODAY FOR FULL INFORMATION AND TELL US WHAT MACHINE YOU NOW OWN. THE ADDRESS IS:**

**KNITTING, Dept. T-1, 1128 Crenshaw Blvd., Los Angeles, Calif. - 90019**

# NOTES TO KNIT BY . . .

## STITCH AND ROW GAUGE

KNIT A SAMPLE SWATCH . . . before you begin to knit any garment . . . for this is the MOST IMPORTANT STEP toward the correct size and the proper fit of any garment you wish to make. You MUST use the SAME YARN for your sample swatch that you will use to knit your garment and your sample swatch must be knitted large enough and using several different tension numbers on your machine. When you have done this, then you can determine the number of stitches and the number of rows in a two-inch measure. KNITTING MAGAZINE PATTERNS give you 3 tensions to try and one of them should give you the correct stitch and row gauge if you are using the yarn we recommend or a similar weight yarn. Here is the way to make your sample swatch.

Cast on over a sufficient number of needles to produce a swatch at least 4 inches wide. (If the pattern calls for 16 stitches to 2", then  $16 \times 2 = 32$  stitches to cast on). Now knit 4 inches of rows at the first suggested tension number. (If the pattern calls for 22 rows to 2",  $22 \times 2 = 44$  rows to knit). Knit 2 rows using a contrast color, change to the next higher tension and with garment yarn knit another 4", knit 2 rows with contrast color, change to the 3rd higher tension and knit another 4" and then bind off.




Roll the swatch into a cylinder over its length and pull on both ends, unroll it and stretch it diagonally by pulling on the four corners. Allow the swatch to rest and settle (preferably overnight) and then using a stitch gauge or a ruler, count the number of stitches over a 2" width, then the number of rows over a 2" length in EACH of the 3 tensions. Select the tension number that produces the stitches and rows called for in the pattern. If none of them are correct, you are most likely using the wrong weight of yarn.




## READING OF CHARTS


You will notice the instructions start at the bottom of the Chart and work UP. Follow the charts exactly as written and providing your sample stitch and row gauge is correct, your garment will come out the right size. Please remember that the section of garment as it is knitted on the machine, faces the same way as the Charts are in this magazine. Where two front pieces are needed, (or any other part of a garment that needs two sections) only one section is normally shown and the second section is usually made with reverse shapings. Set in sleeves are usually identical, but raglan sleeves have to be knitted with reverse shapings for the second sleeve.


## READING OF SYMBOLS

To simplify Pattern Knitting, we use Symbols in the Line Drawings and the Chart Diagrams. In the Line Drawings the symbols are shown and are to be read as you look at them while knitting a garment. For instance, if

a Purl stitch faces you, the Purl stitch Symbol  is shown; if a knit stitch faces you (as when using the Ribber) then this Symbol  is shown. The Symbol  at the top of the Line Drawing is the center of the garment section and you use this as a guide for setting up the needles.

The following Symbols    are used for Eyelet Designs in the Line Drawings and also for Full Fashion shaping on the Charts. The Line Drawings have row numbers on the right side. Missing Row numbers are always knitted straight or plain.

In Holding Position Designs  selected needles are pushed into holding position for the stated number of rows. The numbers of rows appear at the right of the Line Drawings; Example: 1-4 means knit Rows 1 to 4; 5 to 7 means knit Rows 5 to 7, etc. This same Symbol is also shown on the Charts and is used for putting needles into holding position for Short Rows. The

Symbol  on the Charts is used to put needles back into working position when knitting Short Rows.

A number in a box stands for the number of rows to be knitted between shapings. Make shapings first, then knit the necessary number of rows. If for instance it reads:

1 st. 8 x



1 st. 10 x



As you will be reading the instructions from the bottom up, here is the way you will follow them: . . . Decrease or increase (depending on the direction of the garment outline) 1 st. at the row where the shaping begins, then knit 8 rows, make the next decrease, then knit 8 rows, until you have decreased (or increased) 1 st. 10 x and you have knitted 8 rows after each decrease (or increase) (1 st. 10 x + 8 rows 10 x). Now begin the first decrease (or increase) for the shaping (which has to be made 8 x) in every 6th row. Decrease (or increase) 1 st. first, then knit 6 rows until you have decreased 1 st. 6 x and after each decrease (or increase) have knitted 6 rows (1 st. 8 x + 6 rows 8 x).

Where shapings are given without a boxed number as on most armholes, necklines, etc., make the shapings on every second row (on each side of course).

(See below for more Pattern Stitch Symbols.)

### PATTERN STITCH SYMBOLS



= knit stitch



= purl stitch



= empty needle (leave in working position)



= needle not used (in the out of work position)



= needle in the holding position



= Needles back into working position.



= 2 stitches on 1 needle - either transferred from the right side or the left side, then put the needle into holding position



= needle holding 2 stitches. Stitch has been transferred from the LEFT



= needle holding 2 stitches. Stitch has been transferred from the RIGHT



= 3 stitches on 1 needle. The 1st and 3rd stitch in a group of 3 needles has been hung on the 2nd or center needle.



= Center of Garment Section.



= Number of rows to be knitted between shapings.

The diagrams (Line Drawings) for pattern work are followed just as they are shown and are to be read as you look at them while knitting the garment.

open darts



closed darts





YARNS  
64

 **knitking**

---

This entire outfit was made with beautiful KNITTING YARNS and instructions are included in this issue.

The cost of the yarn for the Jacket and Hot Pants for a Size 8 (Subita Dragon 3-ply) is \$16.80 plus \$1.00 for Shipping.

The Pullover and Leotites yarn (Subita 2 x 3) cost for Size 8 is \$15.60 plus \$1.00 for Shipping.

The Jacket and Hot Pants for Size 10 (Crocus Crepe) cost is \$24.00 plus \$1.00 for Shipping.

The Pullover and Leotites (Crocus Crepe) cost for Size 10 is \$20.40 plus \$1.00 for Shipping.

The Jacket and Hot Pants for Size 12 (Double Knitting) is \$23.14 plus \$1.35 for Shipping.

The Pullover and Leotites (Subita 2 x 4) cost for Size 12 is \$24.00 plus \$1.00 for Shipping.

*California residents, please include 5% Sales Tax.*

---

Order direct from KNITTING YARNS, 1128 Crenshaw Blvd., Los Angeles, 90019.