


# Knits for Joy



VOL. 131


## SYMBOLS/ABBREVIATIONS

S.D.	— Stitch Dial (The figure in circle indicates Stitch Dial number.)
pos.	— position
sec.	— section
st. (sts.)	— stitch or stitches
nd. (nds.)	— needle or needles

## Electronic Knitter SK890 & Optional Pattern Controller EC1

Chunky "handknit" looks are easy and fun to knit on the SK890 because creative simplicity is built right in. Ideal for all the exciting fashion yarns, the SK890 is light as a feature to use due to its superb design and friction free carriage rollers. It's guaranteed to turn your dreams into knitted designs!

The EC1 Pattern Controller provides multi-functional, cost saving electronic intelligence. Adding the EC1 to your SK840, SK860 or SK890 is a must. Insert any one of the preprinted design cards into the EC1 and you can reproduce any section of the pattern at any time. In addition you can create a wide variety of pattern variations such as reversing colour and direction, mirror image, as well as vertical and horizontal expansion. All this is achieved at the simple touch of a finger.



Your letters to "Knits for Joy" are always welcomed at the following address:—

S.S.C.  
P.O. Box 5095, Tokyo International  
Tokyo, 100-31, Japan

© Silver Knitting Institute, Tokyo, Japan  
Printed in Japan 90.11.4M(41)

## LADY'S CARDIGAN WITH SCARF

Finished measurements Size: cm.

	A	B	C
Bust	112	116	120
Cardigan Length	62	64	66
Sleeve Length	55	57	59

### Material/others:

Extra thick yarn (100% wool)

Cardigan.....750gs.

Scarf.....200gs.

1 button (2cm. in diameter)

2 pairs of snaps (1 cm. in diameter)

Machine.....9mm. pitch machine with ribber.

### Tension Gauges:

15 sts. by 24 rows over a swatch of Rib. Stitch with S.D. at ④/④.

17 sts. by 24 rows over a swatch of Cable Stitch with S.D. at ④/④.

\* When calculating the number of sts. for back, fronts and sleeves, take an average of the above numbers of sts. (The average number of sts. is 16.)


16 sts. by 30 rows over a swatch of K1.P1. Rib. with S.D. ②/②.

Knit back, fronts and sleeves in Cable and Rib. Stitch.

The patterns are given on page 4 ~ 5 and instructions are as follows.

### To knit


#### Back





- Following the contour line, knit up to the shoulder shaping neckline by decreasing sts.
- Transfer the sts. from the knitter to the ribber and remove the knitting from the machine with waste knitting.

### Sleeves




- Knit the right and left sleeve alike.
- Knit sleeves in the same way as done for back but shaping underarm by increasing sts. at both edges.

### To make up

- Pin out each piece to correct size and shape and press with a steam iron.
- Join both shoulders on the machine.
- Join the upper edge of sleeve to armhole on the machine.
- Join side and underarm seams by blind stitch.
- Finish the open sts. of the neckline with slip stitch using a crochet hook.
- With the right side facing you, work 1 crab and 1 chain stitch alternately using the crochet hook along the neckline and both front edges.
- Give the final press.
- Sew on two pairs of snaps in each pos. and a button in the left pos. for snap of the right front as decoration.

### Scarf



- Knit the required number of rows for scarf in the same way as done in steps (1) ~ (3) for back.
- Change the Swing Indicator from H-3 to P-3.
- Transfer the sts. with arrow mark to their corresponding nds. as shown at the top of the right to rearrange the nds. for K1.P1. Rib.

Center(0)





- Knit the required number of rows in K1.P1. Rib.
- Knit several rows in Tubular knitting with waste yarn and remove the knitting from the machine.
- Close the open sts. of the last row using a tapestry needle as illustrated below.
- Pin out the scarf to correct size and press with a steam iron.
- Work edging in the same way as done for front edge using the crochet hook.


### How to close stitches (K1.P1. Rib.)

The illustration below shows how the yarn is guided through the stitches.

(Use one of the following methods according to the stitch alignment.)







Front & Back

Trace the patterns on the blank pattern paper or set this paper in the Knit Contour.